

## Personal Lockers

Technical specification for Personal Lockers	
personal locker "type"	ppl
personal locker mount path	/afs/eos/lockers/people
<b>container volume</b>	
container volume name	ppl.[ <i>UnityID</i> ]
container mount point	/afs/eos/lockers/people/[ <i>firstinit.</i> ]/[ <i>UnityID</i> ]
container volume permissions	system:administrators rliwdka system:authuser l itecs-admin:lockeraudit rl [ <i>UnityID</i> ] rl
<b>sub volumes</b>	<b>types: {private,public,web}</b>
<b>private volumes</b>	<b>{volume(s) optional}</b>
quota (initial/max)	50MB / 1024MB
volume permissions	system:administrators rliwdka itecs-admin:lockeraudit rl [ <i>UnityID</i> ] rliwdka
initial volume name (relative to container)	[ <i>containervolume</i> ].prv
initial volume mount (rel. to container)	/private
additional volume name(s)	[ <i>containervolume</i> ].v01..[ <i>containervolume</i> ].v99
additional volume mounts (rel. to initial)	/private/[ <i>somemount</i> ] (work with owner)
<b>public volumes</b>	<b>{volume(s) optional}</b>
quota (initial/max)	50MB / 1024MB
volume permissions	system:administrators rliwdka system:authuser rl itecs-admin:lockeraudit rl [ <i>UnityID</i> ] rliwdka
initial volume name	[ <i>containervolume</i> ].pub
initial volume mount (rel. to container)	/public
additional volume name(s)	[ <i>containervolume</i> ].v01..[ <i>containervolume</i> ].v99
additional volume mounts (rel. to initial)	/public/[ <i>somemount</i> ] (work with owner)
<b>web volume</b>	<b>{volume optional}</b>
quota (initial/max)	50MB / 1024MB
volume permissions	system:administrators rliwdka itecs-admin:lockeraudit rl engr:www-servers rl [ <i>UnityID</i> ] rliwdk
volume name	[ <i>containervolume</i> ].www
volume mount (rel. to container)	/www
additional volume mount	/afs/eos/engrservers/www/people/[ <i>UnityID</i> ]
web server url	http://people.engr.ncsu.edu/[ <i>UnityID</i> ]